

__licenseInstallation

Qube has both Supervisor and Worker license keys

You'll have only one supervisor key, but can have any number of worker keys.

Qube has a single license file for all license keys

Qube has license keys for both the Supervisor and the Workers, but the keys for both are installed on the supervisor.

- you can have only a single supervisor license key in your license file.
- you can have any number of worker license keys in your license file, they will be added together.

Without a license file, the supervisor will not dispatch jobs



New in Qube 6.10

Prior to Qube 6.10, a supervisor would dispatch jobs on up to 2 hosts, but now a license file is necessary **in all cases**.

License keys are valid for the major.minor Qube version they are issued for, and ALL versions before that



Do not upgrade your supervisor to a newer major.minor until you have installed the license key for the newer version. Failing to do so **will result in your supervisor refusing to dispatch jobs** until you either install the updated license keys or downgrade your supervisor.

License keys are issued for a particular version of Qube. A key for a version *ahead* of your current version will work, but you can't use an *older* key with a newer version.

- a key for 6.9 is valid for any version of 6.9-x (6.9-0, 6.9-2, etc), and any version before 6.9 (6.8-x, 6.7-x, etc)
- a key for 6.9 is **invalid** for 6.10-0 and onwards.

Online License Retrieval

Contents

- [The License File](#)
- [Installing with Qube! UI](#)
- [Installing Licenses by Hand](#)
 - [License file location](#)
- [Verifying License Installation](#)
 - [With the Qube! UI](#)
 - [By Command-line](#)
- ["I have 0 licenses now..."](#)
- [Optionally, setup Metered Licensing](#)

The License File

The Qube! license file contains the keys for both the Supervisor and Worker, and:


- **Must be installed on the supervisor.** The location is documented later on this page - see [Installing Licenses by Hand](#)
- **Must be named qb.lic**

Qube! license keys can be installed either with the Qube! UI or creating and editing the license file by hand. License file updates take effect immediately, there is no need to restart the Supervisor or Workers.


Installing with Qube! UI

The simplest way to install the Qube! license is with the Qube! UI, via the Administration->Install license on (Local) Supervisor menu item. This option is greyed out if you are not on the Supervisor.

Windows users: you **must** start the Qube! UI with "Run as Administrator", even when you are logged in as an admin-equivalent or local administrator. This is due to Window's "elevated privileges" security policy.



A dialog will appear, prompting you to copy & paste your license strings. You have the option of either adding the keys to your existing licenses or replace the license file.



! Please note that the license string does not include "----- < snip - do not include this line in the license file > -----" lines that are in your license email.

Installing Licenses by Hand

You can also install license keys by editing the license file directly.



- Make a backup copy of the license file before editing it.
- You must use a text editor capable of saving out plaintext.
- The license file must end with the extension ".lic".
- Saving the license file with a .rtf, .txt, .doc, extension or in any format other than plaintext will render your license file invalid.

License file location


Depending on the supervisor's operating system, the qb.lic file is located in:

- Linux & macOS: /etc/qb.lic
- Windows XP, XP-64, Win2K3: C:\Windows\qb.lic
- Windows Win2K8, Vista, Win7: C:\ProgramData\Pfx\qube\qb.lic

Verifying License Installation

With the Qube! UI

Immediately after installing the license, the Qube! UI title bar should update and reflect the new license count.



By Command-line

You can verify the license count with the qbping utility. In this example, all worker licenses for this supervisor will use metered licenses.

```
jburk-15-mbPro:LaunchAgents jburk$ qbping  
  
supervisor - active - tag: 10.0.1.101 78:4F:43:68:FD:7C 7.0-1c rel-7.0-0006 osx - - host - 0/0  
unlimited licenses (metered=0/300) - mode=0 (0).
```

The license counts displayed can be interpreted in the following manner:

- 0/0 unlimited licenses: 0 licenses in use, 0 worker licenses installed
- metered=0/300: metered licensing is enabled and in effect, currently using 0 licenses of a maximum of 300 metered worker licenses

"I have 0 licenses now..."

If after license installation you now show 0 licenses, you haven't yet installed the worker keys, or the license file has become invalid (perhaps it got saved out with an extension other than .lic, or saved in RTF or Wordpad format). Check the license file with a plaintext editor

Optionally, setup Metered Licensing

You can run a supervisor without any worker licenses if you have setup Metered Licensing. See [Getting Started with Metered Licensing](#)